

Kin2. User Guide

Juan R. Terven, Diana M. Cordova

1 Introduction

The Kin2 Toolbox for Matlab is an easy to use set of classes and functions that encapsulate the Microsoft Kinect 2 SDK. It is mostly based on C++ through mex files. The current version contains two classes and 30 functions divided in different features such as coordinate mapping, skeleton tracking, 3D reconstruction, and face gestures recognition. 封装 映射 重建

2 Image Acquisition

Kinect three provides three sources of video images: RGB, depth, and infrared. The resolution of the RGB images is 1920×1080 , the depth and infrared have resolution of 512×424 .

The first step is to generate a Kin2 object specifying the image sources we wish to obtain from the Kinect2. The available sources are color, depth, infrared and body. For example:

```
k2 = Kin2('color', 'depht', 'infrared')
```

generates a Kin2 object named k2 that we can use to gather color, depth and/or infrared frames from the Kinect2.

To extract frames from the Kinect cameras we call the updateKin2 function on the Kin2 object. For example:

```
validData = k2.updateKin2
```

Note that this function gets data from the Kinect and save it in an internal buffer in Matlab. If there was a valid frame, the function returns 1 if not, returns 0.

To actually get the frames in Matlab variables we call the corresponding functions on the Kin2 object: getDepth, getColor, and getInfrared.

Listing 1.1 shows how to create a Kin2 object to gather and display video from these three sources. In this example, we created we three figures, one for each source and update the content each valid frame.

Listing 1.1. Kin2 initialization and data acquisition

```
1 clear all
2 % Create Kinect 2 object and initialize it
3 % Select sources as input parameters.
4 % Available sources: 'color', 'depth', 'infrared' and 'body'
5 k2 = Kin2('color','depth','infrared');
6
7 % Create the figures for the images
```

```

8 figure, h1 = imshow(zeros(424,512,'uint16'),[0 4000]);
9 colormap('Jet'), colorbar;
10 figure, h2 = imshow(zeros(1080,1920,3,'uint8'),[]);
11 figure, h3 = imshow(zeros(424,512,'uint16'),[0 8000]);
12 set(gcf,'keypress','k=get(gcf,'currentchar');');
13
14 % Loop until pressing 'q' on infrared figure
15 k=[];
16 while true
17     % Read frames from Kinect
18     validData = k2.updateData;
19
20     % Before accessing the data,
21     % make sure that a valid frame was acquired.
22     if validData
23         depth = k2.getDepth;
24         color = k2.getColor;
25         infrared = k2.getInfrared;
26
27         set(h1,'CData',depth);
28         set(h2,'CData',color);
29         set(h3,'CData',infrared);
30     end
31
32     % If user presses 'q', on the infrared figure exit loop
33     if ~isempty(k)
34         if strcmp(k,'q'); break; end;
35     end
36
37     pause(0.02)
38 end
39
40 close all
41
42 % Close kinect object
43 k2.delete;

```

3 Coordinate Mapping

Coordinate Mapping is used to perform two tasks [1]: (1) map between locations on the depth image and their corresponding locations on the color image and viceversa and (2) project and unproject from 2D image space to 3D camera space. 2D image space refers to the depth or color image coordinates.

In practice, to perform any mapping, you should always update the Kin2 data calling updateKin2 on the Kin2 object and see if there are valid data as shown in listing 1.

3.1 Depth Space

In depth space, $x = 1, y = 1$ corresponds to the top left corner of the image and $x = 512, y = 424$ is the bottom right corner of the image. When we need the depth value or z , simply sample the depth image at the row/column in question, and use that value as z (in millimeters). For example: if `depth` is a depth image obtained with `getDepth`, we get the depth as `z = depth(row,col)`.

Map Depth to Color The color sensor and depth sensor have a small offset between each other and different resolutions. To map between locations on the depth image and their corresponding locations on the color image `Kin2` provides the function

```
ptColor = k2.mapDepthPoints2Color(ptDepth)
```

where `ptColor` and `ptDepth` are a $n \times 2$ matrix of image coordinates.

For a complete code example see the mapping demo in section 7.1.

Map Depth to Camera and Point Cloud A common operation on the depth image is to generate a 3D point cloud of the scene. For this, `Kin2` provides a couple of methods. The first one consists of mapping a set of coordinates from depth space to camera space for example. This method is useful if you only need to map few points from depth space to camera space:

```
ptCam = k2.mapDepthPoints2Camera(ptDepth)
```

where `ptDepth` is a $n \times 2$ matrix (n x,y coordinates), and `ptCam` is $n \times 3$ matrix (n x,y,z coordinates).

If you want to get the complete point cloud, i.e. to map all the points from depth space to camera space, `Kin2` provides:

```
pointCloud = k2.getPointCloud
```

where `pointCloud` is a $N \times 3$ camera space values. And $N = 512 \times 424 = 217088$. Note that coordinates with no depth information can not be mapped to camera space, and these coordinates are return as `inf` or `-inf` in camera space.

For a complete code example see the camera mapping demo in section 7.3 and the point cloud demo in section 7.2.

Map Depth to Infrared Depth and infrared images come from the same sensor so there is no offset and no change in resolution. To map a point from depth to infrared just sample the same coordinates.

3.2 Color Space

In color space, $x = 1, y = 1$ corresponds to the top left corner of the image and $x = 1920, y = 1080$ is the bottom right corner of the image. A common practice in RGBD processing is to obtain the depth or world coordinates of specific color space coordinates. For example if we find features in the color image and we want to know their depth or location in the world.

Map Color to Depth Kin2 provides the following function to map from color space to depth space.

```
ptDepth = k2.mapColorPoints2Depth(ptColor)
```

where `ptColor` and `ptDepth` are a $n \times 2$ matrix of image coordinates.

For a complete code example see the mapping demo in section 7.1.

Map Color to Camera Kin2 also provides a function to map from color space to camera space.

```
ptCam = k2.mapColorPoints2Camera(ptColor)
```

where `ptColor` is a $n \times 2$ matrix (n x,y coordinates), and `ptCam` is $n \times 3$ matrix (n x,y,z coordinates).

For a complete code example see the camera mapping demo in section 7.3.

3.3 Camera Space

Camera space refers to the 3D coordinate system (right-handed) used by Kinect. The coordinate system is defined as follows [1]:

- The origin (x=0, y=0, z=0) is located at the center of the IR sensor on Kinect. infrared ray
- X grows to the sensors left
- Y grows up (note that this direction is based on the sensors tilt)
- Z grows out in the direction the sensor is facing
- 1 unit = 1 meter

Kinect2 SDK provides mapping capabilities between camera space and depth or color space that is 2D projections.

Map Camera to Depth Kin2 provides a function to map from 3D camera coordinates to depth image coordinates:

```
ptDepth = k2.mapCameraPoints2Depth(ptCam)
```

where `ptCam` is $n \times 3$ matrix (n x,y,z coordinates) and `ptDepth` is a $n \times 2$ matrix (n x,y coordinates).

For a complete code example see the camera mapping demo in section 7.3.

Map Camera to Color Kin2 also provides a function to map from 3D camera coordinates to color image coordinates.

```
ptColor = k2.mapCameraPoints2Color(ptCam)
```

where `ptCam` is $n \times 3$ matrix (n x,y,z coordinates) and `ptColor` is a $n \times 2$ matrix (n x,y coordinates).

For a complete code example see the camera mapping demo in section 7.3.

4 Body Tracking

Kin2 provides easy access to Kinect 2 body tracking capabilities.

To enable body tracking, you must **indicate** the *body* source when creating the Kin2 object. For example:

```
k2 = Kin2('color','depth','body')
```

creates a Kin2 object capable of fetching color and depth frames and also body tracking information.

Then to get the body data Kin2 provides the function `getBodies` that you can call after updating the Kin2 data. For example:

```
bodies = k2.getBodies
```

where `bodies` is a structure array with one element for each body (6 bodies maximum). Each element contains the following information:

- **Position:** a 3x25 matrix containing the x,y,z of the 25 joints in camera space coordinates
- **TrackingState:** state of each joint. These can be: NotTracked=0, Inferred=1, or Tracked=2
- **LeftHandState:** state of the left hand
- **RightHandState:** state of the right hand

The `RightHandState` and `LeftHandState` properties provide information about the state of each of the player's hands. You can use this information to determine if a player is interacting with an object in the title's world [2]. The states returned are: Open, Closed, Lasso, NotTracked, Unknown.

Once you have the joints position in 3D space you can map them to depth or color space for visualization using the `mapCameraPoints2Depth` or `mapCameraPoints2Color` functions described in section 3.3, for example:

```
posDepth = k2.mapCameraPoints2Depth(bodies(1).Position')
posColor = k2.mapCameraPoints2Color(bodies(1).Position')
```

For a complete example of body tracking see section 7.4.

4.1 Drawing Bodies

Kin2 provides functions to draw the bodies on the depth image or the color image freeing the developer from this tedious task.

To draw bodies on depth or color image you can use the `drawBodies` function as follows:

```
k2.drawBodies(d.ax,bodies,'depth',5,3,15)
```

where the six parameters are the following:

1. Image axes. Figure axes obtained with Matlab `axes` function.
2. Bodies structure. Bodies returned by the `getBodies` function.
3. Destination image. 'depth' or 'color'.
4. Joints' size. Circle radius.
5. Bones' Thickness.
6. Hands' Size.

For a complete example of body tracking and drawing see section 7.4.

5 Face Processing

Kin 2 provides two levels of face processing: simple face processing and HD face.

5.1 Simple Face Processing

With this functionality We can detect and track the face and recognize eight facial properties listed in table 1. The `getFaces` method returns a MATLAB structure array containing the following face data for each detected face:

- `FaceBox`: rectangle containing the user’s face.
- `FacePoints`: five alignment points located on the user’s face.
- `FaceRotation`: face orientation expressed as Euler angles: *pitch*, *yaw*, *roll*.
- `FaceProperties`: read-only key/value pairs. See Table 1 for a description of each property. Each property can have the following values: Unknown, No, Maybe, or Yes.

Table 1. Face Properties contained in the `FaceProperties` field of the structure array returned with `getFaces`.

Name	Description
Happy	The user is showing a smile.
Engaged	Combines results from Looking Away and Eye Closed to determine if user is engaged with content.
WearingGlasses	The user is wearing glasses.
LeftEyeClosed	The user’s left eye is closed.
RightEyeClosed	The user’s right eye is closed.
MouthOpen	The user’s mouth is open.
MouthMoved	The user’s mouth moved
LookingAway	Determines if the user is looking away from the content

5.2 HD Face Processing

HD Face provides amazing face processing capabilities: (1) face capture with 94 shape units and a high definition face model with 1347 mesh vertices, (2) face tracking of 17 animation units (AUs) expressed as a numeric weight varying between 0 and 1. *Kin2* provides access to these HD face capabilities with the `getHDFaces` method. This method returns a structure array containing the following fields for each detected face:

- `FaceBox`: rectangle containing the user’s face.
- `FaceRotation`: face orientation expressed as Euler angles: *pitch*, *yaw*, *roll*.
- `HeadPivot`: center of the head, which the face may be rotated around. The origin is located at the Kinect’s optical center, the Z axis is pointing towards a user, the Y axis is pointing up and the X axis is pointing to the right. The units are in meters.
- `AnimationUnits`: 17 animation units (AUs) expressed as a numeric weight varying between 0 and 1. Refer to [3] for a list of these animation units.
- `ShapeUnits`: 94 shape units (SUs) expressed as a numeric weight varying between -2 and +2. Refer to [4] for a list of these shape units, also called *shape deformations*.
- `FaceModel`: high definition face model with 1347 mesh vertices. Refer to [5] for a list of these high detail face points.

6 3D Reconstruction

The *Kin2* toolbox includes a version of *Kinect Fusion* taken from the Kinect for Windows SDK 2.0. To initialize the 3D reconstruction engine, *Kin2* provides the method `KF_init` that can be configured for different reconstruction’s resolution and size. The method prototype is the following:

```
KF_init(voxelsPerMeter, voxelsX, voxelsY, voxelsZ, gpu)
```

For example if we set `voxelsPerMeter` to 256 we will have a resolution of $1000mm \div 256vpm = 3.9mm/voxel$, then if we set `voxelsX`, `voxelsY`, and `voxelsZ` to 384 we will have a reconstruction of $384voxels \div 256vpm = 1.5m$ wide reconstruction and we will require at least $384 \times 384 \times 384 \times 4$ bytes per voxel = 227MB of memory. The final parameter `gpu` if *true*, the algorithm will use the GPU otherwise, it will use the CPU.

Once initialized, each call to `KF_update` updates the volume reconstruction with new views.

7 Complete Code examples

7.1 Mapping Demo

```
1 % MAPPINGDEMO Illustrates how to map points between depth ...
   and color images
2 %
3 % Usage:
4 %   - Press 'd' to select 5 points on the depth image. ...
   The selected points
5 %   will be mapped from depth to color and will be ...
   displayed on both
6 %   images in red.
```

```

7 % - Press 'c' to select 5 point on the color image. The ...
   selected points
8 %   will be mapped from color to depth and will be ...
   displayed on both
9 %   images in green.
10 % - Press 'q' to exit.
11 %
12 % Juan R. Terven, October 2015.
13 % jrterven@hotmail.com
14
15 addpath('Mex');
16 clear all
17 close all
18
19 % Create a Kin2 object and initialize it
20 % Select sources as input parameters.
21 % Available sources: 'color', 'depth', 'infrared' and 'body'
22 k2 = Kin2('color','depth');
23
24 % images sizes
25 d_width = 512; d_height = 424; outOfRange = 4000;
26 c_width = 1920; c_height = 1080;
27
28 % Color image is to big, let's scale it down
29 COL_SCALE = 0.5;
30
31 % Create matrices for the images
32 depth = zeros(d_height,d_width,'uint16');
33 color = ...
   zeros(c_height*COL_SCALE,c_width*COL_SCALE,3,'uint8');
34
35 % Images used to draw the markers
36 depthAdditions = zeros(d_height,d_width,3,'uint8');
37 colorAdditions = ...
   zeros(c_height*COL_SCALE,c_width*COL_SCALE,3,'uint8');
38
39 % depth stream figure
40 d.h = figure;
41 d.ax = axes('units','pixels','drawmode','fast');
42 d.im = imshow(depth,[0 255]);
43 title('Depth Source (press q to exit)')
44 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
   listen keypress
45
46 % color stream figure
47 c.h = figure;
48 c.im = imshow(color,[]);
49 title('Color Source (press q to exit)');
50 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
   listen keypress

```



```

51
52
53 % Loop until pressing 'q' on any figure
54 k=[];
55
56 disp('Instructions:')
57 disp('Press d to select a point on the depth image')
58 disp('Press c to select a point on the color image')
59 disp('Press q on any figure to exit')
60
61 while true
62     % Get frames from Kinect and save them on underlying ...
        buffer
63     validData = k2.updateData;
64
65     % Before processing the data, we need to make sure ...
        that a valid
66     % frame was acquired.
67     if validData
68         % Copy data to Matlab matrices
69         depth = k2.getDepth;
70         color = k2.getColor;
71
72         % update depth figure
73         depth8u = uint8(depth*(255/outOfRange));
74         depth8uc3 = repmat(depth8u,[1 1 3]);
75         set(d.im,'CData',depth8uc3 + depthAdditions);
76
77         % update color figure
78         color = imresize(color,COL_SCALE);
79         set(c.im,'CData',color + colorAdditions);
80     end
81
82     % If user presses 'd' enter to points selection mode ...
        on the depth image
83     % If user presses 'c' enter to points selection mode ...
        on the color image
84     % If user presses 'q', exit loop
85     if ~isempty(k)
86         if strcmp(k,'d')
87             figure(d.h);
88             title('Clic the image to sample 5 points');
89
90             % Grab 5 points
91             [x,y] = ginput(5);
92             disp('Input depth coordinates');
93             disp([x y])
94             % Draw the selected points in the depth image

```

```

95         depthAdditions = ...
           insertMarker(depthAdditions,[x ...
              y], 'Color','red');
96
97         % Using the mapping, map the points from ...
           depth coordinates to color coordinates
98         % Input and output: n x 2 matrix (n points)
99         colorCoords = k2.mapDepthPoints2Color([x y]);
100        colorCoords = colorCoords * COL_SCALE; % ...
           scale the color coordinates
101
102        disp('Output color coordinates');
103        disp(colorCoords);
104
105        % Draw the output coordinates on the color image
106        colorAdditions = insertMarker(colorAdditions, ...
           colorCoords, 'Color','red', 'Size',10);
107
108        k = [];
109    elseif strcmp(k, 'c')
110        figure(c.h);
111        title('Click the image to sample 5 points');
112
113        % Grab 5 points
114        [x,y] = ginput(5);
115        disp('Input color coordinates');
116        disp([x y]);
117
118        % Draw the selected points in the color image
119        colorAdditions = ...
           insertMarker(colorAdditions,[x ...
              y], 'Color','green', 'Size',5);
120
121        % Using the mapping, map the points from ...
           color coordinates to depth coordinates
122        % Input and output: n x 2 matrix (n points)
123        depthCoords = ...
           k2.mapColorPoints2Depth([x/COL_SCALE ...
              y/COL_SCALE]);
124
125        disp('Output depth coordinates')
126        disp(depthCoords);
127
128        % Draw the output coordinates on the depth image
129        depthAdditions = ...
           insertMarker(depthAdditions,depthCoords, 'Color','green');
130
131
132        k = [];
133    end

```

```

134
135         if strcmp(k, 'q'); break; end;
136     end
137
138     pause(0.02)
139 end
140
141 % Close kinect object
142 k2.delete;
143
144 close all

```

7.2 Point Cloud Demo

```

1  % POINTCLOUDDemo illustrates how to use the Kin2 class to ...
   get the
2  % pointcloud in camera space
3  %
4  % Juan R. Terven, January 2016.
5  % jrterven@hotmail.com
6
7  addpath('Mex');
8  clear all
9  close all
10
11 % Create Kinect 2 object and initialize it
12 % Select sources as input parameters.
13 % Available sources: 'color', 'depth', 'infrared' and 'body'
14 k2 = Kin2('depth');
15
16 % images sizes
17 depth_width = 512; depth_height = 424; outOfRange = 4000;
18
19
20 % Create matrices for the images
21 depth = zeros(depth_height, depth_width, 'uint16');
22 pointCloud = zeros(depth_height*depth_width, 3);
23
24 % depth stream figure
25 figure, h1 = imshow(depth, [0 outOfRange]);
26 title('Depth Source (press q to exit)')
27 colormap('Jet')
28 colorbar
29 set(gcf, 'KeyPress', 'k=get(gcf, 'currentchar');'); % ...
   listen keypress
30
31 % point cloud figure

```

```

32 figure, hpc = ...
    plot3(pointCloud(:,1),pointCloud(:,2),pointCloud(:,3),'.');
33 title('Point Cloud (press q to exit)')
34 axis([-3 3 -3 3 0 4])
35 xlabel('X'), ylabel('Y'), zlabel('Z');
36 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
37
38 % Loop until pressing 'q' on any figure
39 k=[];
40
41 disp('Press q on any figure to exit')
42 while true
43     % Get frames from Kinect and save them on underlying ...
    buffer
44     validData = k2.updateData;
45
46     % Before processing the data, we need to make sure ...
    that a valid
47     % frame was acquired.
48     if validData
49         % Copy data to Matlab matrices
50         depth = k2.getDepth;
51
52         % update depth figure
53         depth(depth>outOfRange) = outOfRange; % truncate ...
        depth
54         set(h1,'CData',depth);
55
56         pointCloud = k2.getPointCloud;
57         set(hpc,'XData',pointCloud(:,1),'YData',pointCloud(:,2),'ZData',pointCloud(:,3))
58
59     end
60
61     % If user presses 'q', exit loop
62     if ~isempty(k)
63         if strcmp(k,'q');
64             break;
65         elseif strcmp(k,'p');
66             pause;
67         end;
68     end
69
70     pause(0.02)
71 end
72
73 % Close kinect object
74 k2.delete;
75
76 close all;

```

7.3 Camera Mapping Demo

```
1 % MAPPINGTOCAMDEMO Illustrates how to map points between ...
   depth and color images
2 %
3 % Usage:
4 %   - Press 'd' to select a point on the depth image. The ...
   selected point
5 %     will be mapped from depth to camera and the ...
   resulting coordinates are
6 %     printed on command window. Then the camera ...
   coordinates are mapped
7 %     back to depth space and printed to command window.
8 %   - Press 'c' to select a point on the color image. The ...
   selected point
9 %     will be mapped from color to camera and the ...
   resulting coordinates are
10 %    printed on command window. Then the camera ...
   coordinates are mapped
11 %    back to color space and printed to command window.
12 %   - Press 'q' to exit.
13 %
14 % Juan R. Terven, October 2015.
15 % jrterven@hotmail.com
16
17 addpath('Mex');
18 clear all
19 close all
20
21 % Create Kinect 2 object and initialize it
22 % Select sources as input parameters.
23 % Available sources: 'color', 'depth', 'infrared' and 'body'
24 k2 = Kin2('color','depth');
25
26 % images sizes
27 depth_width = 512; depth_height = 424; outOfRange = 4000;
28 color_width = 1920; color_height = 1080;
29
30 % Color image is to big, let's scale it down
31 COL_SCALE = 0.5;
32
33 % Create matrices for the images
34 depth = zeros(depth_height,depth_width,'uint16');
35 color = ...
   zeros(color_height*COL_SCALE,color_width*COL_SCALE,3,'uint8');
```

```

36
37 % Images used to draw the markers
38 depthAdditions = zeros(depth_height,depth_width,3,'uint8');
39 colorAdditions = ...
    zeros(color_height*COL_SCALE,color_width*COL_SCALE,3,'uint8');
40
41 % depth stream figure
42 h1 = figure;
43 hdepth = imshow(depth,[0 255]);
44 title('Depth Source (press q to exit)')
45 set(gcf,'keypress','k=get(gcf,\'currentchar\');'); % ...
    listen keypress
46
47 % color stream figure
48 h2 = figure;
49 hcolor = imshow(color,[]);
50 title('Color Source (press q to exit)');
51 set(gcf,'keypress','k=get(gcf,\'currentchar\');'); % ...
    listen keypress
52
53
54 % Loop until pressing 'q' on any figure
55 k=[];
56
57 disp('Instructions:')
58 disp('Press d to select a point on the depth image')
59 disp('Press c to select a point on the color image')
60 disp('Press q on any figure to exit')
61
62 while true
63     % Get frames from Kinect and save them on underlying ...
        buffer
64     validData = k2.updateData;
65
66     % Before processing the data, we need to make sure ...
        that a valid
67     % frame was acquired.
68     if validData
69         % Copy data to Matlab matrices
70         depth = k2.getDepth;
71         color = k2.getColor;
72
73         % update depth figure
74         depth8u = uint8(depth*(255/outOfRange));
75         depth8uc3 = repmat(depth8u,[1 1 3]);
76         set(hdepth,'CData',depth8uc3 + depthAdditions);
77
78         % update color figure
79         color = imresize(color,COL_SCALE);
80         set(hcolor,'CData',color + colorAdditions);

```

```

81     end
82
83     % If user presses 'd' enter to points selection mode ...
      on the depth image
84     % If user presses 'c' enter to points selection mode ...
      on the color image
85     % If user presses 'q', exit loop
86     if ~isempty(k)
87         if strcmp(k, 'd')
88             figure(h1);
89             title('Click the image to sample a point');
90
91             % Grab 1 points
92             [x,y] = ginput(1);
93             disp('Input depth coordinates');
94             disp([x y])
95             % Draw the selected points in the depth image
96             depthAdditions = ...
                insertMarker(depthAdditions,[x ...
                    y], 'Color', 'red');
97
98             % Map the point from depth coordinates to ...
              camera coordinates
99             % Input: 1 x 2 matrix (1 points, x,y)
100            % Output: 1 x 3 matrix (1 point, x,y,z)
101            camCoords = k2.mapDepthPoints2Camera([x y]);
102
103            disp('Mapped camera coordinates');
104            disp(camCoords);
105
106            % Map the resulting camera point back to ...
              depth space
107            depthCoords = ...
                k2.mapCameraPoints2Depth(camCoords);
108            disp('Mapped depth coordinates');
109            disp(depthCoords);
110
111            k = [];
112        elseif strcmp(k, 'c')
113            figure(h2);
114            title('Click the image to sample 5 points');
115
116            % Grab 1 point
117            [x,y] = ginput(1);
118            disp('Input color coordinates');
119            disp([x/COL_SCALE y/COL_SCALE]);
120
121            % Draw the selected point in the color image

```

```

122         colorAdditions = ...
            insertMarker(colorAdditions,[x ...
                y], 'Color', 'green', 'Size',5);
123
124         % Map the points from color coordinates to ...
            camera coordinates
125         % Input: 1 x 2 matrix (1 points, x,y)
126         % Output: 1 x 3 matrix (1 point, x,y,z)
127         camCoords = ...
            k2.mapColorPoints2Camera([x/COL_SCALE ...
                y/COL_SCALE]);
128
129         disp('Mapped camera coordinates')
130         disp(camCoords);
131
132         % Map the resulting camera point back to ...
            color space
133         colorCoords = ...
            k2.mapCameraPoints2Color(camCoords);
134         disp('Mapped color coordinates');
135         disp(colorCoords);
136
137         k = [];
138     end
139
140     if strcmp(k,'q'); break; end;
141 end
142
143     pause(0.02)
144 end
145
146 % Close kinect object
147 k2.delete;
148
149 close all

```

7.4 Body Tracking Demo

```

1 % BODYDEMO Illustrates how to use the Kin2 object to get ...
    and draw the
2 % Skeleton data
3 %
4 % Juan R. Terven, October 31 2015.
5 % jrterven@hotmail.com
6
7 addpath('Mex');
8 clear all

```



```

9 close all
10
11 % Create Kinect 2 object and initialize it
12 % Select sources as input parameters.
13 % Available sources: 'color', 'depth', 'infrared' and 'body'
14 k2 = Kin2('color','depth','body');
15
16 % images sizes
17 d_width = 512; d_height = 424; outOfRange = 4000;
18 c_width = 1920; c_height = 1080;
19
20 % Color image is to big, let's scale it down
21 COL_SCALE = 1.0;
22
23 % Create matrices for the images
24 depth = zeros(d_height,d_width,'uint16');
25 color = ...
        zeros(c_height*COL_SCALE,c_width*COL_SCALE,3,'uint8');
26
27 % depth stream figure
28 d.h = figure;
29 d.ax = axes('drawmode','fast');
30 d.im = imshow(zeros(d_height,d_width,'uint8'));
31 %hold on;
32
33 title('Depth Source (press q to exit)')
34 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
        listen keypress
35
36 % color stream figure
37 c.h = figure;
38 c.ax = axes;
39 c.im = imshow(color,[]);
40 title('Color Source (press q to exit)');
41 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
        listen keypress
42 %hold on
43
44 % Loop until pressing 'q' on any figure
45 k=[];
46
47 disp('Press q on any figure to exit')
48 while true
49     % Get frames from Kinect and save them on underlying ...
        buffer
50     validData = k2.updateData;
51
52     % Before processing the data, we need to make sure ...
        that a valid
53     % frame was acquired.

```

```

54     if validData
55         % Copy data to Matlab matrices
56         depth = k2.getDepth;
57         color = k2.getColor;
58
59         % update depth figure
60         depth8u = uint8(depth*(255/outOfRange));
61         depth8uc3 = repmat(depth8u,[1 1 3]);
62         d.im = imshow(depth8uc3, 'Parent', d.ax);
63
64         %set(d.im,'CData',depth8uc3);
65
66         % update color figure
67         color = imresize(color,COL_SCALE);
68         c.im = imshow(color, 'Parent', c.ax);
69
70         %set(c.im,'CData',color);
71
72         % Get 3D bodies joints
73         % getBodies returns a structure array.
74         % The structure array (bodies) contains 6 bodies ...
75         %   at most
76         % Each body has:
77         % -Position: 3x25 matrix containing the x,y,z of ...
78         %   the 25 joints in
79         %   camera space coordinates
80         % -TrackingState: state of each joint. These can be:
81         %   NotTracked=0, Inferred=1, or Tracked=2
82         % -LeftHandState: state of the left hand
83         % -RightHandState: state of the right hand
84         bodies = k2.getBodies;
85
86         % Number of bodies detected
87         numBodies = size(bodies,2);
88         disp(['Bodies Detected: ' num2str(numBodies)])
89
90         % first body info:
91         %disp(bodies(1).TrackingState)
92         %disp(bodies(1).RightHandState)
93         %disp(bodies(1).LeftHandState)
94
95         % To get the joints on depth image space, you can ...
96         %   use:
97         %pos2D = ...
98         %   k2.mapCameraPoints2Depth(bodies(1).Position');
99
100        %To get the joints on color image space, you can use:
101        %pos2D = ...
102        %   k2.mapCameraPoints2Color(bodies(1).Position');

```

```

99         % Draw bodies on depth image
100        % Parameters:
101        % 1) image axes
102        % 2) bodies structure
103        % 3) Destination image (depth or color)
104        % 4) Joints' size (circle raddii)
105        % 5) Bones' Thickness
106        % 6) Hands' Size
107        k2.drawBodies(d.ax,bodies,'depth',5,3,15);
108
109        % Draw bodies on color image
110        k2.drawBodies(c.ax,bodies,'color',10,6,30);
111
112    end
113
114    % If user presses 'q', exit loop
115    if ~isempty(k)
116        if strcmp(k,'q'); break; end;
117    end
118
119    pause(0.02)
120 end
121
122 % Close kinect object
123 k2.delete;
124
125 close all;

```

7.5 Face Processing Demo

```

1  % FACEDEMO Illustrates how to use the Kin2 object to get ...
   and draw the
2  % face data
3  %
4  % Note: You must add to the windows path the bin ...
   directory containing the
5  %     Kinect20.Face.dll.
6  %     For example: C:\Program Files\Microsoft ...
   SDKs\Kinect\v2.0_1409\bin
7  %
8  % Juan R. Terven, January 2016.
9  % jrterven@hotmail.com
10
11  addpath('Mex');
12  clear all
13  close all
14

```

```

15 % Create Kinect 2 object and initialize it
16 % Available sources: 'color', 'depth', 'infrared', ...
    'body_index', 'body',
17 % 'face' and 'HDface'
18 k2 = Kin2('color','face');
19
20 % images sizes
21 c_width = 1920; c_height = 1080;
22
23 % Color image is to big, let's scale it down
24 COL_SCALE = 1.0;
25
26 % Create matrices for the images
27 color = ...
    zeros(c_height*COL_SCALE,c_width*COL_SCALE,3,'uint8');
28
29 % color stream figure
30 c.h = figure;
31 c.ax = axes;
32 c.im = imshow(color,[]);
33 title('Color Source (press q to exit)');
34 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
35
36 % Loop until pressing 'q' on any figure
37 k=[];
38
39 disp('Press q on any figure to exit')
40 while true
41     % Get frames from Kinect and save them on underlying ...
        buffer
42     validData = k2.updateData;
43
44     % Before processing the data, we need to make sure ...
        that a valid
45     % frame was acquired.
46     if validData
47         % Get color frame
48         color = k2.getColor;
49
50         % Get the faces data
51         % faces is a structure array with at most 6 ...
            faces. Each face has
52         % the following fields:
53         % - FaceBox: rectangle coordinates representing ...
            the face position in
54         %   color space. [left, top, right, bottom].
55         % - FacePoints: 2 x 5 matrix representing 5 face ...
            landmarks:

```

```

56         % left eye, right eye, nose, right and left ...
           mouth corners.
57         % - FaceRotation: 1 x 3 vector containing: pitch, ...
           yaw, roll angles
58         % - FaceProperties: 1 x 8 vector containing the ...
           detection result of
59         % each of the face properties.
60         % The face properties are:
61         % Happy, Engaged, WearingGlasses, ...
           LeftEyeClosed, RightEyeClosed,
62         % MouthOpen, MouthMoved, LookingAway
63         % The detection results are:
64         % Unknown = 0, No = 1, Maybe = 2, Yes = 3;
65         faces = k2.getFaces;
66
67         % update color figure
68         color = imresize(color,COL_SCALE);
69         c.im = imshow(color, 'Parent', c.ax);
70
71         % Display the faces data:
72         % Parameters:
73         % 1) image axes
74         % 2) faces structure obtained with getFaces
75         % 3) face landmarks size (radius)
76         % 4) display text information?
77         % 5) information font size in pixels
78         k2.drawFaces(c.ax,faces,5,true,20);
79
80     end
81
82     % If user presses 'q', exit loop
83     if ~isempty(k)
84         if strcmp(k,'q'); break; end;
85     end
86
87     pause(0.02)
88 end
89
90 % Close kinect object
91 k2.delete;
92
93 close all;

```

7.6 HD Face Processing Demo

```

1 % FACEHDDMO Illustrates how to use the Kin2 object to ...
  get and display the

```

```

2 % HD face data
3 %
4 % Note: You must add to the windows path the bin ...
    directory containing the
5 %     Kinect20.Face.dll.
6 %     For example: C:\Program Files\Microsoft ...
    SDKs\Kinect\v2.0_1409\bin
7 %
8 % Juan R. Terven, January 2016.
9 % jrterven@hotmail.com
10
11 addpath('Mex');
12 clear all
13 close all
14
15 % Create Kinect 2 object and initialize it
16 % Available sources: 'color', 'depth', 'infrared', ...
    'body_index', 'body',
17 % 'face' and 'HDface'
18 k2 = Kin2('color', 'HDface');
19
20 % images sizes
21 c_width = 1920; c_height = 1080;
22
23 % Color image is to big, let's scale it down
24 COL_SCALE = 1.0;
25
26 % Create matrices for the images
27 color = ...
    zeros(c_height*COL_SCALE,c_width*COL_SCALE,3,'uint8');
28
29 % color stream figure
30 c.h = figure;
31 c.ax = axes;
32 c.im = imshow(color,[]);
33 title('Color Source (press q to exit)');
34 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
35
36 model = zeros(3,1347);
37 figure, hmodel = plot3(model(1,:),model(2,:),model(3,:),'.');
38 %axis([-1 1 -1 1 -1 1])
39 title('HD Face Model (press q to exit)')
40 xlabel('X'), ylabel('Y'), zlabel('Z');
41 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
42
43 % Loop until pressing 'q' on any figure
44 k=[];
45

```

```

46 disp('Press q on any figure to exit')
47 while true
48     % Get frames from Kinect and save them on underlying ...
        buffer
49     validData = k2.updateData;
50
51     % Before processing the data, we need to make sure ...
        that a valid
52     % frame was acquired.
53     if validData
54         % Get color frame
55         color = k2.getColor;
56
57         % update color figure
58         color = imresize(color, COL_SCALE);
59         c.im = imshow(color, 'Parent', c.ax);
60
61         % Get the HDfaces data
62         % the output faces is a structure array with at ...
            most 6 faces. Each face has
63         % the following fields:
64         % - FaceBox: rectangle coordinates representing ...
            the face position in
65         %   color space. [left, top, right, bottom].
66         % - FaceRotation: 1 x 3 vector containing: pitch, ...
            yaw, roll angles
67         % - HeadPivot: 1 x 3 vector, computed center of ...
            the head,
68         %   which the face may be rotated around.
69         %   This point is defined in the Kinect body ...
            coordinate system.
70         % - AnimationUnits: 17 animation units (AUs). ...
            Most of the AUs are
71         %   expressed as a numeric weight varying between ...
            0 and 1.
72         %   For details see ...
            https://msdn.microsoft.com/en-us/library/microsoft.kinect.face.faceshapean
73         % - ShapeUnits: 94 hape units (SUs). Each SU is ...
            expressed as a
74         %   numeric weight that typically varies between ...
            -2 and +2.
75         %   For details see ...
            https://msdn.microsoft.com/en-us/library/microsoft.kinect.face.faceshapede
76         % - FaceModel: 3 x 1347 points of a 3D face model ...
            computed by face capture
77         faces = k2.getHDFaces;
78
79         % Display the HD faces data and face model(1347 ...
            points):
80         % Parameters:

```

```

81         % 1) image axes
82         % 2) faces structure obtained with getFaces
83         % 3) display HD face model vertices(1347 points)?
84         % 4) display text information (animation units)?
85         % 5) text font size in pixels
86
87
88         % Plot face model points
89         if size(faces,2) > 0
90             model = faces(1).FaceModel;
91             set(hmodel, 'XData', model(1,:), 'YData', model(2,:), 'ZData', model(3,:));
92         end
93     end
94
95     % If user presses 'q', exit loop
96     if ~isempty(k)
97         if strcmp(k, 'q'); break; end;
98     end
99
100     pause(0.02)
101 end
102
103 % Close kinect object
104 k2.delete;
105
106 close all;

```

7.7 Kinect Fusion Demo

```

1  % KINECTFUSIONDEMO Illustrates how to use the Kin2 to ...
   perform 3D
2  % reconstruction
3  %
4  % Note: You must add to the windows path the bin ...
   directory containing the
5  %     Kinect20.Fusion.dll
6  %     For example: C:\Program Files\Microsoft ...
   SDKs\Kinect\v2.0_1409\bin
7  %
8  % Juan R. Terven, January 2016.
9  % jrterven@hotmail.com
10
11 addpath(' ../Mex ');
12 clear all
13 close all
14
15 % Create Kinect 2 object and initialize it

```



```

16 % Select sources as input parameters.
17 % Available sources: 'color', 'depth', 'infrared', ...
    'body_index', 'body',
18 % 'face' and 'HDface'
19 k2 = Kin2('color','depth');
20
21 k2.KF_init;
22
23 % images sizes
24 depth_width = 512; depth_height = 424; outOfRange = 4000;
25 color_width = 1920; color_height = 1080;
26
27 % Color image is too big, let's scale it down
28 colorScale = 0.4;
29
30 % Create matrices for the images
31 depth = zeros(depth_height,depth_width,'uint16');
32 volume = zeros(depth_height,depth_width,3,'uint8');
33 color = ...
    zeros(color_height*colorScale,color_width*colorScale,3,'uint8');
34
35 % depth stream figure
36 figure, h1 = imshow(depth,[0 outOfRange]);
37 title('Depth Source (press q to exit)')
38 colormap('Jet')
39 colorbar
40 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
41
42 % color stream figure
43 figure, h2 = imshow(color,[]);
44 title('Color Source (press q to exit)');
45 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
46
47 % volume stream figure
48 figure, h3 = imshow(volume,[]);
49 title('Volume Source (press q to exit)');
50 set(gcf,'keypress','k=get(gcf,'currentchar');'); % ...
    listen keypress
51
52 % Loop until pressing 'q' on any figure
53 k=[];
54 timedFrames = zeros(1,100);
55 disp('Press q on any figure to exit')
56 for i=1:100
57     tic
58     % Get frames from Kinect and save them on underlying ...
        buffer
59     validData = k2.updateData;

```

```

60
61     % Before processing the data, we need to make sure ...
        that a valid
62     % frame was acquired.
63     if validData
64         % Copy data to Matlab matrices
65         depth = k2.getDepth;
66         color = k2.getColor;
67
68         k2.KF_update;
69         volume = k2.KF_getVolumeImage;
70
71         % update depth figure
72         depth(depth>outOfRange) = outOfRange; % truncate ...
            depht
73         set(h1,'CData',depth);
74
75         % update color figure
76         color = imresize(color,colorScale);
77         set(h2,'CData',color);
78
79         % update infrared figure
80         set(h3,'CData',volume);
81     end
82
83     % If user presses 'q', exit loop
84     if ~isempty(k)
85         if strcmp(k,'q'); break; end;
86         if strcmp(k,'m');
87             mesh = k2.KF_getMesh;
88             k=[];
89         end;
90     end
91
92     pause(0.02)
93     timedFrames(i) = toc;
94 end
95
96 % Close kinect object
97 k2.delete;
98
99 close all;

```

References

1. Microsoft: Coordinate mapping. <https://msdn.microsoft.com/en-us/library/dn785530.aspx> (January 2016)
2. Microsoft: Body tracking. <https://msdn.microsoft.com/en-us/library/dn799273.aspx> (January 2016)

3. Network, M.D.: Faceshapeanimations enumeration. <https://msdn.microsoft.com/en-us/library/microsoft.kinect.face.faceshapeanimations.aspx> (January 2016)
4. Network, M.D.: Faceshapedeformations enumeration. <https://msdn.microsoft.com/en-us/library/microsoft.kinect.face.faceshapedeformations.aspx> (January 2016)
5. Microsoft: Highdetailfacepoints enumeration. <https://msdn.microsoft.com/en-us/library/microsoft.kinect.face.highdetailfacepoints.aspx> (January 2016)